CBP 350 Rail Customs Status Information

February 2018





350 Customs Status Information

Functional Group ID=AU

Introduction:

This X12 Transaction Set contains the format and establishes the data contents of the Customs Status Information Transaction Set (350) for use within the context of an Electronic Data Interchange (EDI) environment. The transaction set can be used by the Customs Service (CS) to supply carriers, terminal operators, port authorities and service providers with cargo release and cargo hold information for import shipments. It can also be used by the CS to provide exporters or their agents, carriers, and service providers with information pertaining to export shipments.

This Implementation Guideline uses the ASC X12 7010 Standards Version/Release as its base. The transaction structure has been altered to accommodate U.S. Customs and Border Protection implementation requirements.

Notes:

All transactions will result in a new status notification which will be sent to all parties associated with the manifest.

The trigger for the TS350 release will be a TS358 train Consist or the train is arrived at the US port of Departure (TS353).

Notes:

- 1. The X4 segment is provided for Bill of Lading status notifications.
- 2. The V9 segment is provided for conveyance-level status notifications.

The first occurrence of any of the X415 reference qualifiers 8S (Future Use), OB, or BN is reported on the X4 segment. If more than one of these applies, additional values are reported on the Reference Identifier segment (N9). A Secondary Notify Party (SNP) can only be reported using the N9 segment.

Special Messaging constraints:

- Limit one Interchange (ISA-IEA) per message transmission.
- Limit one message Group (GS-GE) per message transmission.
- Limit one transaction set (ST-SE) of the same Transaction Set Identifier (TS) Code (i.e., 350). Only one is allowed per message transmission.
- Element delimiters used in this transaction will be '*' (asterisk). No blanks between delimiters if element is null.
- Segment delimiters used in this transaction will be one byte with a value of hex '15'.
- A segment delimiter will be the last byte of data in the message transmission data stream.
- Only uppercase AMERICAN ENGLISH alphabetic data will be transmitted.
- ONLY displayable characters found on a standard American English keyboard will be transmitted. Low-values, carriage return characters, or other non-standard characters shall NOT be transmitted.
- 'Not Used' in the left column indicates that a composite or data element will not be used by CBP.
- 'Dep' in the left column indicates that CBP usage of a particular segment or element is Dependent (Conditional) within the CBP application.
- Per the ASC X12 Standard, an 'M' indicates a Mandatory use, 'O' indicates Optional Use and an 'X' indicates a Conditional use.
- CBP requirements may override ASC X12 Standard Mandatory or Conditional usages.
- Maximum allowable message transmission size is 12 megabytes (12,582,912 bytes) of data.

(Last Update: February 2016) ACE v 1.0.1 Rail export

	Pos.	Seg.		Req.		Loop
	<u>No</u> .	<u>ID</u>	<u>Name</u>	Des.	Max.Use	<u>Repeat</u>
M	0050	ISA	Interchange Control Header	M	1	
M	0075	GS	Functional Group Header	M	1	
M	0100	ST	Transaction Set Header	M	1	
	0200	M10	Manifest Identifying Information	O	1	
			LOOP ID - P4			20
	0400	P4	Port Information	O	1	

	0450	V9	Event Detail	O	20	
Not Used	0460	VEH	Vehicle Information	O	10	
Not Used	0465	NM1	Individual or Organizational Name	O	9999	
			LOOP ID - VID			9999
	0470	VID	Conveyance Identification	О	1	
	0480	M7	Seal Numbers	O	5	
	0490	M7A	Seal Number Replacement	O	22	
Not Used	0500	K1	Remarks	О	4	
			LOOP ID - X4			9999
	0600	X4	Customs Release Information	О	1	
	0700	K1	Remarks	O	4	
	0710	N9	Extended Reference Information	O	999	
	0810	N7	Equipment Details	O	999	
			LOOP ID - BA1			999
Not Used	0850	BA1	Export Shipment Identifying Information	О	1	
			LOOP ID - X4			9999
Not Used	0900	X4	Customs Release Information	О	1	
Not Used	0950	K1	Remarks	O	4	
M	1000	SE	Transaction Set Trailer	M	1	
M	1050	GE	Functional Group Trailer	M	1	
M	1100	IEA	Interchange Control Trailer	M	1	

Segment: ISA Interchange Control Header

Position: 0050

Loop: Level:

Usage: Mandatory

Max Use:

Purpose: To start and identify an interchange of zero or more functional groups and

interchange-related control segments

Syntax Notes: Semantic Notes:

Data Element Summary

	Ref.	Data	Data Ele	ment Summar y			
	Kei.	Data					
	Des.	Element	<u>Name</u>		A	ttrib	outes
M	ISA01	I01		formation Qualifier	M	_	ID 2/2
				the type of information in the Authorization	n Inform	ation	1
			Always '04'				
			04	Rail Communications ID			
M	ISA02	102	Authorization In		M	1	AN 10/10
				for additional identification or authorization or the data in the interchange; the type of		tion	is set
				ion Information Qualifier (I01)	1111011110	tion.	15 500
			Always 'SW355' plu				
M	ISA03	I03	Security Informa		M	1	ID 2/2
				the type of information in the Security Info	rmation		
			Always '00'				
			00	No Security Information Present (No Mean I04)	ingful In		
M	ISA04	I04	Security Informa		M		AN 10/10
				entifying the security information about the in the interchange; the type of information			;
				ion Qualifier (I03)	is set by	the	
			Always 10 spaces.				
M	ISA05	105	Interchange ID (Qualifier	M	1	ID 2/2
				ne system/method of code structure used to	designa	te the	e
			sender or receiver Always '02'	ID element being qualified			
			02	SCAC (Standard Carrier Alpha Code)			
M	ISA06	106	Interchange Send		M	1	AN 15/15
141	ISAUU	100		e published by the sender for other parties			AN 15/15
				te data to them; the sender always codes th			e
			sender ID element				
			USCP	Production			
			USCT	Testing			
M	ISA07	105	Interchange ID C		M	_	ID 2/2
				ne system/method of code structure used to ID element being qualified	designa	ie in	e
			Always '02'	12 crement semig quanticu			
			02	SCAC (Standard Carrier Alpha Code)			
M	ISA08	107	Interchange Reco	eiver ID	M	1	AN 15/15
			Identification cod	e published by the receiver of the data; Wh			
			•	r as their sending ID, thus other parties sen	ding to t	hem	will

use this as a receiving ID to route data to them

Receiver Identifier. Will be identical to that of GS03.

M	ISA09	108	Interchange Date Date of the interch		M	1 DT 6/6
			Date as YYMMDD	where:		
			YY	Year		
			MM	Month of Year		
			DD	Day of Month		
M	ISA10	109	Interchange Tim Time of the interc		M	1 TM 4/4
			Time as HHMM wh	nere:		
			НН	Hour		
			MM	Minute		
M	ISA11	I65	Repetition Separ		M	1 AN 1/1
			element; this field of a simple data el	cable; the repetition separator is a delimiter I provides the delimiter used to separate replement or a composite data structure; this value element separator, component element or	eated oo alue mu	ecurrences st be
M	ISA12	I11		atrol Version Number Code the version number of the interchange contr	M ol segme	1 ID 5/5 ents
			007010	Standards Approved for Publication by AS	C X12 P1	rocedures
M	ISA13	I12	Interchange Con	Review Board through October 2012	M	1 N0 9/9
				assigned by the interchange sender		
M	ISA14	I13	_	at Requested Code ender's request for an interchange acknowle	M edgment	1 ID 1/1
			0	No Interchange Acknowledgment Requeste	ed	
M	ISA15	I14		ge Indicator Code whether data enclosed by this interchange e primation	M nvelope	1 ID 1/1 is test,
			P	Production Data		
M	ISA16	I15	a data element; the data elements with	cable; the component element separator is a is field provides the delimiter used to separation a composite data structure; this value ment separator and the segment terminator	rate com	ponent

GS Functional Group Header **Segment:**

Position: 0075

> Loop: Level:

Mandatory Usage:

Max Use:

To indicate the beginning of a functional group and to provide control information

Purpose: Syntax Notes:

Semantic Notes: GS04 is the group date.

- 2 GS05 is the group time.
- The data interchange control number GS06 in this header must be identical to the same data element in the associated functional group trailer, GE02.

Data Element Summary

	Ref.	Data	·
M	Des. GS01	Element 479	Name Functional Identifier Code Code identifying a group of application related transaction sets Always 'AU' AU Customs Status Information (350)
M	GS02	142	Application Sender's Code Code identifying party sending transmission; codes agreed to by trading partners USCP Production USCT Testing
M	GS03	124	Application Receiver's Code M 1 AN 2/15 Code identifying party receiving transmission; codes agreed to by trading partners Receiver Identifier. Will be identical to that of ISA08.
M	GS04	373	Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year Date as CCYYMMDD where: CC Century YY Year MM Month of Year DD Day of Month
M	GS05	337	Time M 1 TM 4/8 Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99) Eastern Standard/Daylight Time used. Time as HHMM where: HH Hour MM Minute
M	GS06	28	Group Control Number M 1 No 1/9 Assigned number originated and maintained by the sender
M	GS07	455	Responsible Agency Code M 1 ID 1/2 Code identifying the issuer of the standard; this code is used in conjunction with Data Element 480 Always 'X'

February 2018

M GS08 480 Version / Release / Industry Identifier Code M 1 AN 1/12

Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed Always '007010'

007010

Standards Approved for Publication by ASC X12 Procedures Review Board through October 2013 Segment: ST Transaction Set Header

Position: 0100

Loop: Level:

Usage: Mandatory

Max Use:

Purpose: Syntax Notes: Semantic Notes: To indicate the start of a transaction set and to assign a control number

- 1 The transaction set identifier (ST01) is used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).
- 2 The implementation convention reference (ST03) is used by the translation routines of the interchange partners to select the appropriate implementation convention to match the transaction set definition. When used, this implementation convention reference takes precedence over the implementation reference specified in the GS08.

	Ref.	Data		
M	<u>Des.</u> ST01	Element 143	Name Transaction Set Identifier Code Code identifying a Transaction Set	Attributes M 1 ID 3/3
			Always '350' 350 Customs Status Information	
M	ST02	329	Transaction Set Control Number Identifying control number that must be unique wir functional group assigned by the originator for a transaction.	
Not Used	ST03	1705	Implementation Convention Reference	O 1 AN 1/35

M10 Manifest Identifying Information **Segment:**

0200 **Position:**

Loop: Level:

Usage: Optional

Max Use:

Purpose: To transmit manifest identifying information

Syntax Notes: If either M1004 or M1010 is present, then the other is required.

If either M1015 or M1016 is present, then the other is required.

1 M1004 is the International Maritime Organization (IMO) Vessel Code maintained in **Semantic Notes:**

Lloyd's Register of Shipping.

M1007 is used for the six-digit Numeric Manifest Sequence Number.

3 M1011 indicates if the transmission involves an in-bond participant. A "Y" indicates it does; an "N" indicates it does not.

M1012 is a unique identification number for the manifest assigned by the originator of the manifest with a maximum length of 15.

M1017 is the type of initial manifest being amended by this transmission.

Required by US Customs and Border Protection. **Notes:**

May have Ocean relationship as SNP.

Data Element Summary

Ref. **Data**

	Des.	Element	Name	<u>A1</u>	trib	utes
M	M1001	140	Standard Carrier Alpha Code Code identifying the Standard Carrier Alpha Code	M	1	ID 2/4
			SCAC of Carrier initiating the inbound manifest.			
M	M1002	91	Transportation Method/Type Code Code specifying the method or type of transportation for the s	M shipment	_	ID 1/2
			Values provided by CBP. R			
M	M1003	26	Country Code Code identifying the country	M	1	ID 2/3
			ISO 2 alpha Country Code from inbound manifest.			
Not Used	M1004	597	Vessel Code	X		ID 1/8
	M1005	182	Vessel Name	O	1	AN 2/28
			Name of ship as documented in "Lloyd's Register of Ships"			
			CBP returns the Train identification for land border crossings. The carrier assigns the Train ID.	border ci	rossi	ng
	M1006	55	Flight/Voyage Number	O		AN 2/30
			Identifying designator for the particular flight or voyage on w CBP provides the Julian date (YYDDD) if a land border crossing.	hich the	carg	go travels
	M1007	127	Reference Identification	0	1	AN 1/80
			Reference information as defined for a particular Transaction specified by the Reference Identification Qualifier	Set or a	s	
			Unique carrier number is provided by CBP in the notification. If new little return '000001' in the notification message.	ot provide	ed, C	BP
Not Used	M1008	380	Quantity	0		R 1/15
	M1009	256	Manifest Type Code	O	1	ID 1/1
			Code identifying the type of manifest transmitted			
			Always 'Z'			
			Z Sent from U.S. Customs to Carriers			
Not Used	M1010	897	Vessel Code Qualifier	X	1	ID 1/1
Not Used	M1011	1073	Yes/No Condition or Response Code	0	1	ID 1/1
Not Used	M1012	127	Reference Identification	O	1	AN 1/80

Not Used	M1013	353	Transaction Set Purpose Code	0	1 ID 2/2
	M1014	346	Application Type Code	0	1 ID 2/2
			Code identifying an operation		
			Value accepted by CBP		
			28 Rail Export Manifest		
Not Used	M1015	580	Amendment Type Code	X	1 ID 1/1
Not Used	M1016	393	Amendment Code	X	1 ID 2/2
Not Used	M1017	256	Manifest Type Code	0	1 ID 1/1

Segment: P4 Port Information

Position: 0400

Loop: P4 Optional

Data

Level:

Ref.

Usage: Optional

Max Use:

Purpose: To transmit identifying information for a port

Syntax Notes: Semantic Notes:

- 1 P401 is used for customs district and port code (census schedule D).
- 2 P402 is the estimated date of arrival.
- **3** P403 is used for number of bills of lading.
- 4 P404 is the Facilities Information and Resources Management System (FIRMS)
- 5 P405 is the estimated time of arrival for P402.
- 6 P406 is the date conveyance departed prior port.
- 7 P407 is the time conveyance departed prior port.

	Des.	Element	Name		<u>A</u>	ttributes
M	P401	310	Location Identifier		M	1 AN 1/30
			Code which identifi	es a specific location		
			When $M1002 = 'R', C$	BP provides the Port of Departure	of the Train from	the U.S.
M	P402	373	Date		M	1 DT 8/8
			•	CYYMMDD where CC represe	ents the first two	ligits of
			the calendar year Estimated Date of Dec	parture from the last U.S. port		
			CC	Century		
				·		
			YY	Year		
			MM	Month of Year		
			DD	Day of Month		
Not Used	P403	380	Quantity		0	1 R 1/15
Not Used	P404	310	Location Identifier	•	O	1 AN 1/30
Not Used	P405	337	Time		0	1 TM 4/8
Not Used	P406	373	Date		0	1 DT 8/8
Not Used	P407	337	Time		0	1 TM 4/8

Segment: V9 Event Detail

Position: 0450

Loop: P4 Optional

Level:

Usage: Optional Max Use: 20

Purpose: To specify information about a specific event Syntax Notes: 1 If V906 is present, then V905 is required.

- 2 If either V910 or V911 is present, then the other is required.
- 3 If V913 is present, then V904 is required.
- 4 If V915 is present, then V909 is required.

Semantic Notes:

- 1 V903 is the event date.
- 2 V904 is the event time.
- 3 V909 is the Standard Point Location Code (SPLC) of the event shown in the V901.
- 4 V910 is the length of the time delay expressed in hours.
- 5 V913 reflects the time zone which the event time reflects.
- 6 V914 is the quantity of the fuel in gallons.
- 7 V915 is the Standard Point Location Code (SPLC) of the secondary point of the delay indicated in the V911.
- **8** V916 is the total number of rail cars associated with the event code in V901.
- 9 V917 is the total number of loaded cars associated with the event code in V901.
- 10 V918 is the total number of empty cars associated with the event code in V901.
- 11 V919 is the total Gross Tons of the cars identified in V916. Includes the gross weight of the loads and the tare weight of the empties.
- 12 V920 is the total outside foot length of the cars identified in V916, rounded off to the nearest foot.

Notes:

This segment will be provided when CBP arrives a train and notifies the carrier. Will also be sent to notify the carrier that the train arrival is overdue, held or released.

Data Element Summary

Ref. Data

 Des.
 Element Name
 Attributes

 M
 V901
 304
 Event Code
 M
 1 ID 3/3

Code identifying the event about which a report is made

Values provided by CBP. In the case of a Stack Car hold that comes from a hold on the bill the CAMIR Appendix D values will be returned.

DPV Departure of conveyance
DPO Departure Overdue
DPC Departure Cancelled
HMI Hold or Miscellaneous

HRE Release from Hold or Miscellaneous

SEI Seized Equipment

SER Seized equipment - removed

SLR Seal replaced SLA Seal added SLC Seal deleted

Not Used V902 106 Event O 1 AN 1/25 V903 373 Date O 1 DT 8/8

Date expressed as CCYYMMDD where CC represents the first two digits of

the calendar year Date of Posting.

Date as CCYYMMDD where:

CC Century

YY Year

MM Month of Year

DD Day of Month

V904 337 Time X 1 TM 4/8

Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)

Time of Posting will be in Eastern Standard/Daylight time. Time as HHMM where:

НН	Hour
MM	Minute

Not Used	V905	19	City Name	X	1 AN 2/30
Not Used	V906	156	State or Province Code	0	1 ID 2/2
Not Used	V907	26	Country Code	0	1 ID 2/3
Not Used	V908	641	Status Reason Code	0	1 ID 3/3
Not Used	V909	154	Standard Point Location Code	X	1 ID 6/9
Not Used	V910	380	Quantity	X	1 R 1/15
Not Used	V911	1274	Train Delay Reason Code	X	1 AN 2/3
Not Used	V912	61	Free-form Information	0	1 AN 1/30
Not Used	V913	623	Time Code	0	1 ID 2/2
Not Used	V914	380	Quantity	0	1 R 1/15
Not Used	V915	154	Standard Point Location Code	0	1 ID 6/9
Not Used	V916	86	Total Equipment	0	1 N0 1/3
Not Used	V917	86	Total Equipment	0	1 N0 1/3
Not Used	V918	86	Total Equipment	0	1 N0 1/3
Not Used	V919	81	Weight	0	1 R 1/10
Not Used	V920	82	Length	0	1 R 1/8

VID Conveyance Identification **Segment:**

Position: 0470

> Loop: VID Optional

Level:

Usage: **Optional**

Max Use:

Ref.

Not Used

Not Used

Not Used

Not Used

Not Used

Not Used

Data

156

26

127

1715

512

761

VID15

VID16

VID17

VID18

VID19

VID20

To identify a conveyance and its attributes **Purpose:**

Syntax Notes: If VID14 is present, then at least one of VID15 or VID18 is required.

- Only one of VID15 or VID18 may be present. 2 3 If VID15 is present, then VID16 is required.
- 4 If VID16 is present, then at least one of VID15 or VID18 is required.
- 5 If VID18 is present, then VID16 is required.

Semantic Notes: 1 VID12 is the Census Schedule K code for the foreign port of loading on a vessel.

- VID13 is the Standard Carrier Alpha Code (SCAC) of the Haulage Rights Carrier. 2
- 3 VID14 is the license plate of the equipment.
- 4 VID15 is the state or province of the license in the VID14.
- 5 VID16 is the country of the license in the VID15 or VID18.
- VID17 is the ACE (Automated Commercial Environment) ID of the equipment identified in the VID03.

X

X

 \mathbf{o}

 \mathbf{X}

 \mathbf{o}

0

1 ID 2/2

1 ID 2/3

1 ID 1/3

1 ID 1/1

1 N0 1/1

1 AN 1/80

7 VID18 is the country subdivision of the license in the VID14.

VID will only be generated outbound if V901 is 'DPV', 'DPO', 'DPC', 'HMI', 'HRE', 'SEI', 'SER', **Notes:** 'SLR', 'SLA', 'SLC'' and the action is against an empty container on the Consist.

Data Element Summary

	Des.	Element	Name	A	ttributes
M	VID01	40	Equipment Description Code	M	1 ID 2/2
			Code identifying type of equipment used for shipment		
			Refer to Export Multimodal Manifest Appendix F		
	VID02	206	Equipment Initial	0	1 AN 1/4
			Prefix or alphabetic part of an equipment unit's identifying nur	mber	
			For contains without initials use 'NONU'.		
M	VID03	207	Equipment Number	M	1 AN 1/15
			Sequencing or serial part of an equipment unit's identifying nu	ımber (pure
			numeric form for equipment number is preferred)		
Not Used	VID04	225	Seal Number	O	1 AN 2/15
Not Used	VID05	225	Seal Number	O	1 AN 2/15
Not Used	VID06	567	Equipment Length	O	1 N0 4/5
Not Used	VID07	65	Height	O	1 R 1/8
Not Used	VID08	189	Width	O	1 R 1/8
Not Used	VID09	24	Equipment Type Code	O	1 ID 4/4
Not Used	VID10	322	Load/Empty Status Code	O	1 ID 1/1
Not Used	VID11	56	Type of Service Code	O	1 ID 2/2
Not Used	VID12	310	Location Identifier	O	1 AN 1/30
	VID13	140	Standard Carrier Alpha Code	O	1 ID 2/4
			Code identifying the Standard Carrier Alpha Code		
			Owner of Equipment Lessor SCAC.		
Not Used	VID14	127	Reference Identification	0	1 AN 1/80

State or Province Code

Reference Identification

Import/Export Code

Country Subdivision Code

Equipment Number Check Digit

Country Code

Segment: M7 Seal Numbers

Position: 0480

Loop: VID Optional

Data

98

Level:

Ref.

M705

Usage: Optional Max Use: 5

Purpose: To record seal numbers used and the organization that applied the seals

Syntax Notes: Semantic Notes:

Not Used

Data Element Summary

Attributes **Element** Name Des. M M701 225 **Seal Number** 1 AN 2/15 Unique number on seal used to close a shipment A valid exporter/carrier seal number associated with this shipment. Cannot include ". " or " - ". Required by CBP for rail usage if additional seals are applied. M702 225 **Seal Number** 1 AN 2/15 Unique number on seal used to close a shipment A valid exporter/carrier seal number associated with this shipment. Cannot include ". " or " - ". Required by CBP for rail usage if additional seals are applied. 225 M703 1 AN 2/15 **Seal Number** 0 Unique number on seal used to close a shipment A valid exporter/carrier seal number associated with this shipment. Cannot include ". " or " - ". Required by CBP for rail usage if additional seals are applied. M704 225 **Seal Number** 1 AN 2/15 0 Unique number on seal used to close a shipment A valid exporter/carrier seal number associated with this shipment. Cannot include ". " or " - ". Required by CBP for rail usage if additional seals are applied.

1 ID 2/3

Entity Identifier Code

Segment: M7A Seal Number Replacement

Position: 0490

Loop: VID Optional

Data

Level:

Ref.

Usage: Optional Max Use: 22

Purpose: To provide an audit trail of seal number changes

Syntax Notes: 1 If either M7A04 or M7A05 is present, then the other is required.

Semantic Notes: 1 M7A01 is the original seal number.

2 M7A02 is the replacement seal number.

3 M7A03 is the date the new seal was installed.

4 M7A04 and M7A05 indicate the party responsible for the seal replacement.

5 M7A06 is a description of why the seal was replaced.

6 M7A07 is the location of the replaced seal on the equipment.

	Kei.	Data					
M	<u>Des.</u> M7A01	Element 225	Seal Numb	per nber on seal used to close a shipment	M	Attril 1	butes AN 2/15
			If it is a seal in Characters ('	rter/carrier seal number associated with this shipment. number it must be provided. It cannot include special ', '-', '/', etc) al that is being replaced			
\mathbf{M}	M7A02	225	Seal Numb	· 	M	1	AN 2/15
				mber on seal used to close a shipment			
			If it is a seal in Characters ('	rter/carrier seal number associated with this shipment. number it must be provided. It cannot include special ', '-', '/', etc) al replacing the seal listed in M7A01			
	M7A03	373	Date	1 6	О	1	DT 8/8
			-	ssed as CCYYMMDD where CC represents the fir	st two	o digit	s of
			the calenda	r year change of seal occurred			
				YMMDD where:			
			CC	Century			
			YY	Year			
			MM	Month of Year			
			DD	Day of Monthr			
	M7A04	98	•	ntifier Code	X	1	ID $2/3$
				flying an organizational entity, a physical			
				operty or an individual oted by CBP:			
			G7	Entity providing Service			
				representative or government official changing			
	M7A05	93	the seal Name		X	1	AN 1/60
	WITAUS)3	Free-form r	name	А	1	AN 1/00
	M7A06	352	Description	n	O	1	AN 1/80
			A free-forn	n description to clarify the related data elements an	d the	ir cont	ent
			Reason for the	he change of seal.			
	M7A07	302	Location o	n Equipment Code	0	1	ID 1/3
				ating a location on a piece of equipment, as observ The rear-end of the equipment is based on the equi			

Codes accepted by CBP:

Complete Equipment, Right and Left C F Front I Interior LF Left Front LIC Left Inner Center LIF Left Inside Front LIR Left Inside Rear LOC Left Outer Center LOF Left Outside Front LOR Left Outside Rear LR Left Rear LS Left Side R Rear R0F Right Outside Front RF Right Front RIC Right Inner Center RIF Right Inside Front ROC Right Outer Center ROR Right Outside Rear RR Right Rear RS Right Side RSC Right Side Center RSF Right Side Front RSR Right Side Rear T Top Top Center TC TF Top Front TR Top Rear U Under

X4 Customs Release Information **Segment:**

0600 **Position:**

> Loop: X4 **Optional**

Level:

Usage: **Optional**

Max Use:

Purpose: To identify items for release

Syntax Notes:

- If either X403 or X404 is present, then the other is required.
- 2 If either X408 or X410 is present, then the other is required.
- 3 If either X415 or X416 is present, then the other is required.
- 4 If X417 is present, then X406 is required.
- 5 If X418 is present, then X403 is required.
- If X419 is present, then X403 is required. 6
- X401 is the unique bill of lading number. **Semantic Notes:** 1
 - 2
 - X402 is used for quantity released.
 - 3 X405 is the date that the disposition code was posted to Customs file.
 - 4 X406 is the time for the disposition specified in X407.
 - 5 X414 is the U.S. Customs and Border Protection (CBP) Facilities Information and Resource Management System (FIRMS) code or the Canadian Customs Sub-Location code.
 - X417 reflects the time zone which the time reflects.
 - X418 is the Customs port of final destination.
 - X419 is the first foreign port of destination.
 - X420 is the disposition code re-sent indicator. A 'Y' value indicates the disposition code is being resent due to a Port of Discharge or Vessel Name change. An 'N' value indicates there was no disposition code re-send required.

Notes:

Elements X415 and X416 are used in the following 2 scenarios:

- 1. An ocean carrier discharges cargo in Canada and then turns it over to the railroad which assigns their SCAC to the bill and nominates the ocean carrier as an SNP. Therefore X415 will be 'OB' for ocean bill and X416 will be the bill of lading number.
- 2. The X411 and X412 Equipment Number elements will be returned for "Equipment -level" Status Notifications which are specific to a given Equipment for a Bill of Lading. When the X411 and X412 Equipment Number elements are not populated, then the Status Notification is assumed to apply to the entire Bill of Lading.

D.C	D - 4 -
Ref.	Data

	Des.	Element	<u>Name</u>		;	<u>Attributes</u>
M	X401	598	Bill of Ladi	ng/Waybill Number	0	1 AN 1/50
			Identificatio	n number assigned to the shipmer	nt by the carrier or cor	solidator
			Bill Issuer Senumber.	quence Number. X409 + X401 com	prise the unique bill of l	ading
M	X402	380	Quantity		0	1 R 1/15
			Numeric val	ue of quantity		
			Quantity of the release.	the disposition provided in the X407.	Quantity can be partial	amount for
Not Used	X403	581	Customs Er	ntry Type Code	X	1 ID 2/3
Not Used	X404	601	Customs En	ntry Number	X	1 AN 1/50
M	X405	373	Date		M	1 DT 8/8
			Date express	sed as CCYYMMDD where CC r	epresents the first two	digits of
			the calendar	•		
			Date of Postir	ng		
			CC	Century		
			YY	Year		
			MM	Month of Year		
			DD	Day of Month		
	X406	337	Time		X	1 TM 4/8
250 DAIL 701	0 (007010) 1 0	1		21		7.1

Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or

HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)

			Time of Posting will be in Eastern Standard/Daylight time.		
			HH Hour		
			MM Minute		
M	X407	35	Bill of Lading Disposition Code Code indicating to a carrier or port authority about po		1 ID 2/3 ading
			A code advising the carrier, port authority, service bureau, taken on a bill of lading. Refer to Export Multimodal Mani		ng action
Not Used	X408	598	Bill of Lading/Waybill Number	X	1 AN 1/50
M	X409	140	Standard Carrier Alpha Code Code identifying the Standard Carrier Alpha Code	M	1 ID 2/4
Not Used	X410 X411	140 206	Standard Carrier Alpha Code Equipment Initial		1 ID 2/4 1 AN 1/4
			Prefix or alphabetic part of an	equipment unit's id	dentifying number
	X412	207	Equipment Number	O	1 AN 1/15
			Sequencing or serial part of an equipment unit's ident numeric form for equipment number is preferred)	ifying number (pu	re
	X413	310	Location Identifier	O	1 AN 1/30
			Code which identifies a specific location		
			CBP Port of processing - Refer to Export Multimodal Man	ifest Appendix L	
			- CBP only returns 4 numeric characters in this field.		
	X414	310	Location Identifier	0	1 AN 1/30
			Code which identifies a specific location		
			Facilities Information Resources Management Systems (FI To Transfer (PTT) move.		
	X415	128	Reference Identification Qualifier	X	1 ID 2/3
			Code identifying the Reference Identification		
			Values provided by CBP.		
			BN Booking Number		
			OB Ocean Bill of Lading		
	X416	127	Reference Identification		1 AN 1/80
			Reference information as defined for a particular Traspecified by the Reference Identification Qualifier For Reference Identifier Qualifier "OB", the Reference Identifier "OB", the Refe		oill of
			lading number.		
			For Reference Identifier Qualifier "BN", the Reference Identifier provided in the inbound manifest.		
Not Used	X417	623	Time Code		1 ID 2/2
Not Used	X418 X419	310 310	Location Identifier Location Identifier	_	1 AN 1/30 1 AN 1/30
	A417	310	Code which identifies a specific location	U	1 AN 1/30
			Foreign Port of Destination. CBP displays 5 numeric cha	racters in this field	
Not Used	X420	1073	Yes/No Condition or Response Code		1 ID 1/1
1101 Oscu	2172U	1073	1 co/1 to Condition of Response Code	U	1 11/1/1

Segment: K1 Remarks

Position: 0700

Loop: X4 Optional

Level:

Usage: Optional Max Use: 4

Purpose: To transmit information in a free-form format for comment or special instruction

Syntax Notes: Semantic Notes:

Notes: Values provided by CBP.

Data Element Summary

Ref. Data

	Des.	Element	Name		Attributes
M	K101	61	Free-form Information	M	1 AN 1/30
			Free-form information		
Not Used	K102	61	Free-form Information	0	1 AN 1/30

Segment: N9 Extended Reference Information

Position: 0710

Loop: X4 Optional

Level:

Usage: Optional Max Use: 999

Purpose: To transmit identifying information as specified by the Reference Identification Qualifier

Syntax Notes: 1 At least one of N902 or N903 is required.

2 If N906 is present, then N905 is required.

3 If either C04003 or C04004 is present, then the other is required.
4 If either C04005 or C04006 is present, then the other is required.

Semantic Notes: 1 N906 reflects the time zone which the time reflects.

2 N907 contains data relating to the value cited in N902.

Notes: Values will be returned if sent in the inbound message

Data Element Summary

Ref. Data

Des.ElementNameAttributesMN901128Reference Identification QualifierM1ID 2/3

Code identifying the Reference Identification

Refer to Export Multimodal Manifest Appendix I.

N902 127 Reference Identification X 1 AN 1/80

Refer to Export Multimodal Manifest Appendix I.

Segment: N7 Equipment Details

Position: 0810

Loop: X4 Optional

Level:

Ref.

Not Used

N724

301

Car Type Code

Usage: Optional Max Use: 999

Purpose: To identify the equipment

Data

Syntax Notes: 1 If either N703 or N704 is present, then the other is required.

If either N705 or N716 is present, then the other is required.
If either N708 or N709 is present, then the other is required.

Semantic Notes: 1 N712 is the owner of the equipment.

2 N723 is the operator or carrier of the rights of the equipment.

Data Element Summary

M	<u>Des.</u> N701	Element 206	Name Equipment Initial Prefix or alphabetic part of an equipment unit's identifying no	0	attributes 1 AN 1/4
			Container Prefix	umoer	
M	N702	207	Equipment Number Sequencing or serial part of an equipment unit's identifying r numeric form for equipment number is preferred) Container Number	M number (1 AN 1/15 pure
Not Used	N703	81	Weight	X	1 R 1/10
Not Used	N704	187	Weight Qualifier	X	1 ID 1/2
Not Used	N705	167	Tare Weight	X	1 N0 3/8
Not Used	N706	232	Weight Allowance	O	1 N0 2/6
Not Used	N707	205	Dunnage	O	1 N0 1/6
Not Used	N708	183	Volume	X	1 R 1/8
Not Used	N709	184	Volume Unit Qualifier	X	1 ID 1/1
Not Used	N710	102	Ownership Code	O	1 ID 1/1
Not Used	N711	40	Equipment Description Code	O	1 ID 2/2
Not Used	N712	140	Standard Carrier Alpha Code	O	1 ID 2/4
Not Used	N713	319	Temperature Control	O	1 AN 3/6
Not Used	N714	219	Position	O	1 AN 1/3
Not Used	N715	567	Equipment Length	O	1 N0 4/5
Not Used	N716	571	Tare Qualifier Code	X	1 ID 1/1
Not Used	N717	188	Weight Unit Code	O	1 ID 1/1
Not Used	N718	761	Equipment Number Check Digit	O	1 N0 1/1
Not Used	N719	56	Type of Service Code	O	1 ID 2/2
Not Used	N720	65	Height	O	1 R 1/8
Not Used	N721	189	Width	O	1 R 1/8
Not Used	N722	24	Equipment Type Code	O	1 ID 4/4
Not Used	N723	140	Standard Carrier Alpha Code	O	1 ID 2/4

0

1 ID 1/4

Segment: ${\bf SE}$ Transaction Set Trailer

Position: 1000

Loop:

Ref.

Level:

Usage: Mandatory

Data

Max Use:

Purpose: To indicate the end of the transaction set and provide the count of the transmitted

segments (including the beginning (ST) and ending (SE) segments)

Syntax Notes: Semantic Notes:

	Des.	Element	<u>Name</u>	A	ttril	outes
M	SE01	96	Number of Included Segments	\mathbf{M}	1	N0 1/10
			Total number of segments included in a transaction set includi segments	ng ST	and S	SE
M	SE02	329	Transaction Set Control Number	M	1	AN 4/9
			Identifying control number that must be unique within the tran functional group assigned by the originator for a transaction se		n set	

Segment: \mathbf{GE} Functional Group Trailer

Position: 1050

Loop:

Level: Usage: Mandatory

Max Use:

Purpose: To indicate the end of a functional group and to provide control information

Syntax Notes:

Semantic Notes: 1 The data interchange control number GE02 in this trailer must be identical to the same data element in the associated functional group header, GS06.

	Ref.	Data	·			
	Des.	Element	<u>Name</u>	A	ttrib	outes
M	GE01	97	Number of Transaction Sets Included	M	1	N0 1/6
			Total number of transaction sets included in the functional gr	oup or		
			interchange (transmission) group terminated by the trailer con	ntaining	this	data
			element			
M	GE02	28	Group Control Number	M	1	N0 1/9
			Assigned number originated and maintained by the sender			

Segment: IEA Interchange Control Trailer

Position: 1100

Loop:

Ref.

Level:

Usage: Mandatory

Data

Max Use:

Purpose: To define the end of an interchange of zero or more functional groups and

interchange-related control segments

Syntax Notes: Semantic Notes:

	Des.	Element	<u>Name</u>	A	ttrib	outes
M	IEA01	I16	Number of Included Functional Groups A count of the number of functional groups included in an in	M terchang	_	N0 1/5
M	IEA02	I12	Interchange Control Number A control number assigned by the interchange sender	M	1	N0 9/9